



VIGC live Preflight profiles for Adobe InDesign

VIGC, june 2019

© **Copyright**

This document is property of VIGC and cannot be distributed without authorization of VIGC.

CONTENT

1	General	4
2	Install	4
3	Use	4
4	Waiver of Liability	6
5	Useful links	6


1 General

The VIGC Live Preflight profiles are based on Ghent Workgroup specifications for PDF preflight. They allow you to check a number of technical issues in an Adobe InDesign® file while designing or editing. It does not replace PDF preflight! Certain checks cannot be done on design level and need to be performed after creation of the PDF file. An overview of the Ghent Workgroup specifications and their details can be found on www.gwg.org.


2 Install

To install the VIGC Live Preflight profiles for Adobe InDesign, use the following instructions:

1. Open Adobe InDesign
2. Go to Window > Output > Preflight
3. Select 'Define profiles' in the upper right drop down menu



4. Click 'Load Profile' in the lower left corner drop down menu



5. Select one of the VIGC Live Preflight profiles
6. Click 'OK' to confirm the installation

ATTENTION

If you want to install more than one VIGC Live Preflight profiles, you need to repeat the previous steps.

3 Use



To use the VIGC Live preflight profiles, look at the live preflight indicator in the bottom bar of Adobe InDesign. A green marker means ok (no errors), red means that there are 'inconsistencies' (xx errors). Double click the 'indicator' to open the preflight menu.

Browse to each Error to see if there is an actual problem or if a certain layout object may need some adjustment.

The latest version of the VIGC live preflight profiles are based on the current GWG 2015 specifications from Ghent Workgroup. If needed, they can also be used for checking designs against the 'older' GWG 1v4 specifications.

ATTENTION

It has been reported that the live preflight function may slow down Adobe InDesign®. If that is the case, you can 'pause' live preflight until you are happy with your design and want to give it a final check. Activating and deactivating live preflight can be done by clicking the arrow next to the live preflight indicator in Adobe InDesign.



4 Waiver of Liability

The VIGC Live Preflight profiles are provided as is, without warranty of any kind, express, implied, or otherwise, including but not limited to the warranties of merchantability, fitness for a particular purpose and noninfringement. In no event will the Ghent Workgroup, the authors of the Live Preflight profiles, or their employers be liable for any claim, damages or other liability, whether in an action of contract, tort or otherwise, arising from, out of, or in connection with the VIGC Live Preflight profiles.

5 Useful links

- www.vigc.be
- www.gwg.org

Strategische Partners



Campus Blairon 5
B-2300 Turnhout
info@vigc.be
+32 (0)14 40 39 90

www.vigc.be